



## Multi Location Module

### Table of Contents

<b>1. What is the Multi Location Module?</b>	<b>2</b>
<b>2. How do I activate this module?</b>	<b>2</b>
<b>3. What's the difference between a location and a region?</b>	<b>2</b>
<b>4. How do I configure a location?</b>	<b>2</b>
4.1 Setup Locations	2
4.2 Address Tab	3
4.3 Phones Tab	4
4.4 Accounting Tab	5
4.5 Defaults Tab	6
4.6 Other Tab	7
4.7 Email Tab	8
<b>5. Where are locations used in the system?</b>	<b>9</b>

## 1. What is the Multi Location Module?


The RentalPoint multi location module is an additional module that may be purchased separately from your main software package. The module allows you to manage your inventory at multiple warehouse locations with the ability to transfer inventory between locations.

## 2. How do I activate this module?

The multi location module is activated via your license file. Please contact our accounts department to purchase the module and we'll send you an update license file ([support@rentp.com](mailto:support@rentp.com)).

## 3. What's the difference between a location and a region?


Depending on your company workflow, locations may be organized into regions. A region is not an actual physical entity, but rather a grouping of locations; it does not hold any inventory. For example, your company may have three warehouses in California and two in New York. You can enable regions and group the California warehouses into one region and the New York warehouses into a second region. The multi location module can be run with or without regions.


 Regions are enabled via Operational #174.

## 4. How do I configure a location?




### 4.1 Setup Locations

The details of all your locations are accessed via **Setup – Locations**. Once a location is saved in the system it can be edited but not removed; This ensures that your historical data is maintained. When the multi location module is activated the system creates a default location. You can change any and all details for this location to make the information relevant to your company.

 Terminology for **location** can be changed via Setup – Parameters – Terminology – General Tab.




#	Location Name	Status	Tax Authority 1	Tax Authority 2	Accounting File	Company Name	Address Line 1	Unit
0	Main Office	Main	GST	PST	C:\RentalPoint\data\Export0.exp	RentalPoint Software	810 Nipissing Dr	Suite 205
1	Shipping Office	Other	N/A	N/A				
2	Delta Transfer Station	Other	N/A	N/A				
3	Supply Store	Other	N/A	N/A				



 Locations cannot be deleted once they are added. Double click to edit a Location.
 

## 4.2 Address Tab

Location Name	The name used within the software (ie. drop down lists, internal reports etc.).
Company Name	The name used on client facing documents (ie. Invoice).
Company Number	Tax number used on client facing documents (ie. Invoice).
Main Address	Also referred to as the billing address.
Map Address	The physical location of the building. Used in the Get Directions functionality.
Status	This option is only used when <b>Auto transfer from satellite locations</b> is enabled. (Setup – Parameters – Transfers). If a satellite location (configured with a Status of <b>Other</b> ) has a shortage, the system can create a transfer from the <b>Main</b> location to the satellite location.
Auto Transfer	If the satellite location has a shortage, this setting determines if the stock is automatically transferred from the Main location to the satellite location.



RP Location Properties

Address | Phones | Accounting | Defaults | Other | Email

Number: 0

Location Name: Main Office

Company Name: RentalPoint Software

Company Number: T-11-222

Main Address | Map Address

Address Line 1: 810 Nipissing Dr

Unit: Suite 205

City: Milton

Province: On

Country: Canada


Postal Code: L9T 4Z9

Status: Main

Auto Transfer:  Yes  No

OK Cancel

## 4.3 Phones Tab



RP Location Properties

Address Phones Accounting Defaults Other Email

Phone Country

Phone Area

Phone

Phone Ext

Fax Country


Fax Area


Fax

OK Cancel

## 4.4 Accounting Tab


When integrating with an accounting package, this field determines where the transaction file is exported to.

 You can configure account integration via Accounts #21.



## 4.5 Defaults Tab

The defaults used when creating a new booking for this location.



The screenshot shows a software dialog box titled "Location Properties" with a close button (X) in the top right corner. The dialog has several tabs: "Address", "Phones", "Accounting", "Defaults" (which is the active tab), "Other", and "Email".


Under the "Defaults" tab, there are four dropdown menus:

- Tax Authority 1: GST
- Tax Authority 2: PST
- Freight Delivery: Lucys Transport - Ground
- Freight Pickup: Erb X - Ground

At the bottom of the dialog, there are two buttons: "OK" (with a green checkmark icon) and "Cancel" (with a red X icon).


## 4.6 Other Tab

The default location where all your RTF custom templates are stored. When users add templates to the template list, the system defaults to this folder.



## 4.7 Email Tab

Configure email settings that can be used for your operators.



RP Location Properties

Address Phones Accounting Defaults Other Email

Email Address

SMTP Address(Host)

SMTP Port

SSL/TLS

My smtp server requires authentication

Default Standard Email Text





## Multi Location Module

### 5. Where are locations used in the system?

Locations are used throughout RentalPoint. Here's a quick overview of the areas that use locations:

Availability Utilities	Select a location for the availability calendar, plot sheet and running balance.
Bookings	Save your orders for a location. Stock quantities are pulled from that location.
Cross Rentals	
Transfers	
Secondary Scope	The main scope in RentalPoint can be restricted based on a location.
Operator Privileges	Configure access rights to setup locations, select the location scope and change the location scope. Can also restrict access to the 'transfer to' drop down.
Add Stock	Select the location that you want to add stock to.
Archive Booking	Auto transfers stock to the receiving location.
Stocktake	Location scope to perform an inventory check on a per location basis.
Asset Listing Report	Report on assets at a particular location.
AR Audit Trail	Run the report for a particular location.
Cash Receipts	
Invoice Register	
Statements	